


## Pairing with Bluetooth in Windows


The Bluetooth pairing method differs depending on the Windows operating system. Follow the appropriate procedure.

### ❖ In Windows XP

1. On the Control Panel, click “Bluetooth Devices”.



2. On the “Devices” tab, click [Add].




3. When the Add Bluetooth Device Wizard is displayed, set up the Star POS device as instructed on the screen\*, and then click [Next].

\* See the "Hardware Manual" for more information on operating the Star POS device.



4. Select the Bluetooth device you want to add from the list of devices displayed, and then click [Next]. If multiple Bluetooth devices are found, you can right-click the Star POS device, select [Properties], and then check the Bluetooth address to specify the Star POS device you want to pair.




### Checking the Bluetooth address


<b>TSP650II</b>	The Bluetooth address is listed under ***Bluetooth Information*** on the test print sheet. To print a test sheet, turn on the printer while holding down the Feed button.
<b>SAC10EBi</b>	The Bluetooth address is written on the label attached to the product.

5. Select "Use the passkey found in the documentation", enter the passkey (PIN key\*) for the Star POS device for which you want to perform pairing, and then click [Next].

\* See the "Hardware Manual" for more information for PIN key.





6. If pairing is successful after entering the PIN key, the Add Bluetooth Device Wizard is complete. The "COM serial ports assigned to your device" displayed here are necessary when making the Star POS device's communication settings. After the wizard is complete, you can check these ports from the "COM Ports" tab in "Bluetooth Devices" from the Control Panel. When pairing is complete, the following screen is displayed.



## ❖ In Windows Vista


1. On the Control Panel, click "Bluetooth Devices". And click "Add Wireless Device".



- When the Pair with a wireless device window is displayed, set up the Star POS device as instructed on the screen\*, and then click [Next].

\* See the "Hardware Manual" for more information on operating the Star POS device.


- Select the Bluetooth device you want to add from the list of devices displayed, and then click [Next]. If multiple Bluetooth devices are found, you can right-click the Star POS device, select [Properties], and then check the Bluetooth address to specify the Star POS device you want to pair.




#### Checking the Bluetooth address

<b>TSP650II</b>	The Bluetooth address is listed under ***Bluetooth Information*** on the test print sheet. To print a test sheet, turn on the printer while holding down the Feed button.
<b>SAC10EBi</b>	The Bluetooth address is written on the label attached to the product.



- When the following confirmation dialog box appears. Click the "Don't show this message again for this device".



5. When pairing is complete, the following screen is displayed.




6. You can check the virtual COM port assigned by pairing the Bluetooth device from the "COM Ports" tab in "Bluetooth Devices" from the Control Panel. This information is necessary when making the Star POS device's communication settings.



## ❖ In Windows 7 / 8


1. On the Control Panel, click "Devices and Printers". And click "Add a Device".



2. When the Pair with a wireless device window is displayed, set up the Star POS device as instructed on the screen\*, and then click [Next].

\* See the "Hardware Manual" for more information on operating the Star POS device.



3. Select the Bluetooth device you want to add from the list of devices displayed, and then click [Next]. If multiple Bluetooth devices are found, you can right-click the Star POS device, select [Properties], and then check the Bluetooth address to specify the Star POS device you want to pair.



### Checking the Bluetooth address

<b>TSP650II</b>	The Bluetooth address is listed under ***Bluetooth Information*** on the test print sheet. To print a test sheet, turn on the printer while holding down the Feed button.
<b>SAC10EBi</b>	The Bluetooth address is written on the label attached to the product.

4. When pairing is complete, the Star POS device is added to the Printers and Devices screen.





5. To check the virtual COM port assigned by pairing the Bluetooth device, go to the Devices and Printers screen, and then check the "Hardware" tab in Properties for the device that was added.

